


Nisqually Keyboard Layout and Fonts Bundle v.2 | ChromeOS | User Guide

Welcome!

Thanks for downloading the Nisqually Keyboard Layout and Fonts Bundle v.2! Once you've installed it, you'll be able to type beautiful Nisqually anywhere on your computer – including word documents, social media and emails. This keyboard layout is also available for MacOS, Windows, Android and iOS.

How to install the keyboard layout

1


To begin, hit the “Everything Button” or the icon in the bottom left corner  and navigate to the Chrome Webstore. Search for “Nisqually”

2

Click “Nisqually Keyboard”, click “Add to Chrome”, then Click “add extension”
Now, click the gear button to go to Settings, then select the Language and inputs menu and the “Input methods” submenu. Click Add input methods and then check the box next to “Nisqually” in the “Suggested” keyboards.

How to turn on the keyboard layout



To start typing in Nisqually, just click the **Input menu** (“US”) in the bottom right corner of your screen and select **Nisqually keyboard**. When you are finished, just click the menu again and select your other keyboard layout. You can switch between your keyboard layouts more quickly by pressing **control** + **space** .





How to uninstall the keyboard layout


- 1 Open the Chromium browser and type “chrome://extensions” into the address line. Then Search for “Nisqually”
- 2 Find the “Nisqually Keyboard” extension and click “Remove”. Then click “Remove” again in the confirmation popup.

How to use the keyboard layout



The Nisqually keyboard replaces much of the QWERTY layout with special characters needed for the Nisqually language. Holding Shift + the key, produces the the upper character and pressing a key without Shift produces the lower character as shown above.

The orange   keys shift states produce a combining circumflex and combining comma above for extra compatibility with fonts. These can be applied by moving the cursor directly after the character you wish them to be applied to.

Holding down the  key on the right side of the space bar makes the keys behave as they were in the “Default” English keyboard layout without requiring you to turn off the Nisqually keyboard layout. You might find this function helpful if you are typing a Nisqually text that requires only one or two English characters.

NOTE: Some software renders fonts differently and may not work perfectly with the combining circumflex or combining comma above. If you have issues, try typing the orange shift keys multiple times to get the diacritics to properly show.

User support

If you need any assistance in using this product, please phone **1-202-640-2280** or email **customersupport@languageconservancy.org**.